

```
H:\TestDisk\testdisk-6.13.win\testdisk-6.13\testdisk_win.exe
TestDisk 6.13, Data Recovery Utility, November 2011
Christophe GRENIER <grenier@cgsecurity.org>
http://www.cgsecurity.org

Disk /dev/sdd - 1999 GB / 1862 GiB - CHS 243074 255 63
Partition                Start      End      Size in sectors
>D HPFS - NTFS            0 32 33 243074 177 48 3904976393
D HPFS - NTFS             0 33 2 6526 243 53 104853472 [Win XP Bkpl]
D HPFS - NTFS             1 1 1 127482 254 63 2047998267 [Foto Bkpl]
D HPFS - NTFS             6526 244 23 13053 200 11 104853472 [Data Bkpl]
D HPFS - NTFS            13053 200 44 142374 200 42 2077542368 [Foto Bkpl]
D HPFS - NTFS            13053 200 44 143467 216 45 2095101920 [Foto Bkpl]
D HPFS - NTFS            13053 200 44 143595 117 10 2097151968 [Foto Bkpl]
D HPFS - NTFS            127483 1 1 140230 254 63 204796557 [Data Bkpl]
D HPFS - NTFS            140231 1 1 145329 254 63 81915372 [Setup Bkpl]
D HPFS - NTFS            143595 117 43 148817 32 15 83886048 [Setup Bkpl]
D HPFS - NTFS            145330 1 1 170825 254 63 409593177
D HPFS - NTFS            148817 32 48 169703 202 35 335544288 [M3? Bkpl]
D FAT16 >32M            169703 203 36 179493 254 63 157279591
D FAT16 >32M            170826 0 33 191223 39 48 327680278

Structure: Ok. Use Up/Down Arrow keys to select partition.
Use Left/Right Arrow keys to CHANGE partition characteristics:
*Primary bootable P=Primary L=Logical E=Extended D=Deleted
Keys A: add partition, L: load backup, I: change type, P: list files,
Enter: to continue
NTFS, 1999 GB / 1862 GiB
```